AD-R172 956 MOVEPLAN (10) (A UNIT MOVEMENT PLANNING AID) USERS MANUAL (U) COMBINED ARMS OPERATIONS RESEARCH ACTIVITY FORT LEAVENMORTH KS D KONCZAL ET AL. APR 86 F/G 9/2 NL



CHANGE CONTRACT CONTRACT CONTRACT CONTRACT CONTRACT CONTRACT

CARREST PRESENT



APRIL 1986

CAORA/TD-4/86


AD-A172 956

ACN 70876

MOVEPLAN (1.0)

(A UNIT MOVEMENT PLANNING AID)

USERS MANUAL



TECHNICAL DOCUMENT CAORA/TD-4/86

TIC FILE COPY

STUDIES AND ANALYSIS DIRECTORATE
COMBINED ARMS OPERATIONS RESEARCH ACTIVITY
FORT LEAVENWORTH, KANSAS

86-3667

to position is unlimited.

86 10 6 114

4D-A172 956

REPORT D	N PAGE			Form Approved OMB No 0704 0188 Exp Date Jun 30 1986	
TA REPORT SECURITY CLASSIFICATION UNCLASSIFIED		16 RESTRICTIVE MARKINGS			
2a SECURITY CLASSIFICATION AUTHORITY		3 DISTRIBUTION AVAILABILITY OF REPORT			
26 DECLASSIFICATION / DOWNGRADING SCHEDU	LE		or public re		;
4 PERFORMING ORGANIZATION REPORT NUMBE	R(S)	5 MONITORING	ORGANIZATION RE	PORT N	UMBER(S)
CAORA/TD-4/86	·				
6a NAME OF PERFORMING ORGANIZATION U.S. Army Combined Arms 6b. OFFICE SYMBOL (If applicable)		7a NAME OF MONITORING ORGANIZATION			
Operations Research Activity	ATOR-CAS-CF				
6c ADDRESS (City, State, and ZIP Code)		7b. ADDRESS (City, State, and ZIP Code)			
Fort Leavenworth, KS 66027-52	20				
80 NAME OF FUNDING SPONSORING ORGANIZATION USACAURA, ATTN:	86 OFFICE SYMBOL	9 PROCUREMEN	T INSTRUMENT IDE	NTIFICA	TION NUMBER
ATOR-CAS-CF, Ft. Leavenworth, KS 66027-5220	(If applicable)				İ
KS 66027-5220 8c ADDRESS (City, State, and ZIP Code)	L <u> </u>	10 SOURCE OF	FUNDING NUMBER	5	
, 200 100 200 200 200 200 200 200 200 200		PROGRAM	PROJECT	TASK	WORK UNIT
		ELEMENT NO.	NO	NO	ACCESSION NO
11 TITLE (Include Security Classification)			<u> </u>	<u> </u>	ACN: 70876
MOVEPLAN (1.0) (A Unit Movemen	t Planning Aid)	Users Manua	1 (U)		
12 PERSONAL AUTHOR(S) Mr. Derek Konczal, Mrs. Martha	Robinette MA.1	Joromo A 1	20005		
13a TYPE OF REPORT 13b TIME CO	OVERED	14 DATE OF REPO	ORT (Year, Month,	Day) 1	5 PAGE COUNT
Final Users Manual FROM	ro	Ap	ril 1986		60
16 SUPPLEMENTARY NOTATION					
17 COSATI CODES	18 SUBJECT TERMS (C	Continue on revers	se if necessary and	identify	by block number)
FIELD GROUP SUB GROUP	MOVEMENT, Brig	gade, Command Control, Planning, Model			
	Development, D	ecision Aid	s, Movement	Plann	ing Aid (MOVEPLAN)
19 ABSTRACT (Continue on reverse if necessary	and identify by block n	umber)			
This manual provides general information and a detailed tutorial to users of MOVEPLAN (1.0). MOVEPLAN (1.0) is an automated tool to assist U.S. Army personnel to perform the task of unit movement planning. MOVEPLAN (1.0) is an appropriate tool for planning administrative or tactical movement of multiple units along a single route, from a common start point (SP) to a common release point (RP). MOVEPLAN (1.0) is also appropriate for use by tactical planners to develop estimates of the time required to execute phases of a maneuver operation. Thorough study of this manual is essential to proper use of MOVEPLAN (1.0). MOVEPLAN (1.0) was developed by the U.S. Army Combined Arms Operations Research Activity (CAORA), Ft. Leavenworth, Kansas. This program is designed for an IBM or compatible microcomputer w/CPT, a disk drive, and a printer. Components include the Users Manual and the 5 1/4-inch diskette, MOVEPLAN (1.0). An evaluation questionnaire is provided in this manual. Recommendations for changes and improvements to MOVEPLAN (1.0) are encouraged.					
UNITED SAME AS A	PT DTIC USERS	UNCLASSIF	IED		
Mr. Derek Konczal		226 TELEPHONE (913) 684	(Include Area Code -4309) 22c C	TOR-CAS-CF

Studies and Analysis Directorate
Combined Arms Operations Research Activity (CAORA)
Fort Leavenworth, Kansas 66027-5220

MOVEPLAN (1.0)
(A Unit Movement Planning Aid)
Users Manual

by

Mr. Derek Konczal Mrs. Martha Robinette MAJ Jerome A. Jacobs

ACN 70876

Approved by

JAMES T. PITTMA

Colonel, FA

Director, Studies and Analysis Directorate



(THIS PAGE INTENTIONALLY LEFT BLANK)

SOSSION COOLOGEN SESSION CLOCOCO SOSSION LILLIAN SOSSION SOSSION

TABLE OF CONTENTS

<u>Page</u>
TITLE PAGEi
TABLE OF CONTENTS
LIST OF FIGURES
LIST OF TABLES
ABSTRACT
INTRODUCTION
Users Manual Purpose
Background
Developmental Approach
Hardware and Software Requirements
Users Manual Organization
MODEL DESCRIPTION
Model Definitions
Model Application
Model Capabilities and Limitations
Model Operation4
Model Configuration4
Model Organization4
Performance
Data Base6
General Description of Inputs, Processing, Outputs
TECHNICAL OPERATIONS
Initiation Procedures
Tut. or ial
Utilization of Model Outputs
Recovery and Error Correction Procedures
SUMMARY
General 16
Assistance
Obtaining MOVEPLAN (1.0)
APPENDIX A - Data Input Sheet and Sample Data
APPENDIX B - Data Input Prompts and Sample Responses
APPENDIX C - Change Data Prompts and Sample Responses
APPENDIX D - Sample Output
APPENDIX E - MOVEPLAN Evaluation Questionnaire (User Feedback Form)E-1
APPENDIX F - Distribution

LIST OF FIGURES

		Page
1. 2. 3. 4. 5. 6. 7. 8. 9.	MOVEPLAN organization. Input routine. Calculation routine. Output routine. Title and main menu screen. Sample data input sheet with sample data. General program information. Movement rate guidelines. Input prompt for choice 9, listing of files.	5 6 7,8 9
	LIST OF TABLES	
		Page
١.	MOVEPLAN error messages	- 16

ABSTRACT

This manual provides general information and a detailed tutorial to users of MOVEPLAN (1.0). MOVEPLAN (1.0) is an automated tool to assist U.S. Army personnel to perform the task of unit movement planning. MOVEPLAN (1.0) is an appropriate tool for planning administrative or tactical movement of multiple units along a single route, from a common start point (SP) to a common release point (RP). MOVEPLAN (1.0) is also appropriate for use by tactical planners to develop estimates of the time required to execute phases of a maneuver operation. Thorough study of this manual is essential to proper use of MOVEPLAN (1.0). MOVEPLAN (1.0) was developed by the U.S. Army Combined Arms Operations Research Activity (CAORA), Ft. Leavenworth, Kansas. This program is designed for an IBM or compatible microcomputer w/CRT, a disk drive, and a printer. Components include the Users Manual and the 5 1/4-inch diskette, MOVEPLAN (1.0). An evaluation questionnaire is provided in this manual. Recommendations for changes and improvements to MOVEPLAN (1.0) are encouraged.

(THIS PAGE INTENTIONALLY LEFT BLANK)

ASSOL DESCRIPTION OF THE PROPERTY OF THE PROPE

MOVEPLAN (1.0)

USERS MANUAL

1. INTRODUCTION.

- a. <u>Users Manual Purpose</u>. The purpose of this manual is to provide general information and a tutorial of procedures to train users in the proper use of MOVEPLAN (1.0). The manual does not address the detailed design of the software but does provide necessary information to use the program properly.
- b. <u>Background</u>. MOVEPLAN (1.0) is an automated tool which was developed by the U.S. Army Combined Arms Operations Research Activity (CAORA), Fort Leavenworth, Kansas. MOVEPLAN (1.0) was developed as a tool to assist U.S. Army personnel to perform the task of unit movement planning. MOVEPLAN (1.0) was developed as a task within the Command and Staff Decision Aids Project. The requirement for a movement planning or time/distance analysis tool was identified during the AirLand Battle Study. MOVEPLAN (1.0) was developed in response to the requirement. Several alternative approaches were investigated to satisfy the requirement. The alternatives included simple spreadsheet equations and a U.S. Army Command and General Staff College (CGSC) application. However, the alternatives were restrictive in design and did not deal with the variety of movement conditions encountered during tactical operations. MOVEPLAN (1.0) is a computer simulation which accounts for most of the conditions for a single-route tactical movement.
- c. <u>Developmental Approach</u>. MOVEPLAN (1.0) was designed to automate many of the manual procedures involved in unit movement planning. However, MOVEPLAN (1.0) does not do all the steps in the movement planning process. The user must gather data on units, the route, and unit movement tactical standing operating procedures (TSOP's) and then must input this information on a microcomputer. The microcomputer computes the data and prints a report containing a movement table and a summary of inputs. MOVEPLAN (1.0) provides the benefits of responsiveness and accuracy over manual procedures. Thorough study of this manual and tutorial is essential to proper use of MOVEPLAN (1.0).
- d. <u>Hardware and Software Requirements</u>. This program is written in compiled BASIC and is designed for an IBM or compatible microcomputer w/CRT, a disk drive, and a printer. MOVEPLAN (1.0) requires less than 512 KB of memory. Components include the MOVEPLAN (1.0) Users Manual and the 5 1/4-inch diskette, MOVEPLAN (1.0). The diskette contains the executable progam, some associated text files, and a demonstration file. A set of MOVEPLAN Information Briefing Slides is also available through the Command and Control Microcomputer Users Group at Fort Leavenworth. Information on obtaining MOVEPLAN (1.0) is provided in section 4c.
- e. Users Manual Organization. The following sections of this manual provide general information on the capabilities and limitations of MOVEPLAN (1.0). A set of key definitions is provided in section 2, Model Description. A step-by-step tutorial which explains the "how to" for each major procedure may be found in section 3, Technical Operations. The appendixes provide examples and a survey form which may be used to provide suggestions for

program improvements. Information on obtaining assistance in using MOVEPLAN (1.0) and information on obtaining the program itself are found in section 4, Summary.

2. MODEL DESCRIPTION.

ST 1000000 BURNING RELEASED

a. Model Definitions.

- (1) Maximum pace. The maximum rate of march for the lead (pace) vehicle of the force and may not be exceeded by any vehicle. It is equal to the maximum speed of the slowest vehicle in the force.
- (2) Average vehicle length. The average vehicle length (in meters) for all vehicles in the column.
- (3) Vehicle interval. The distance (in meters) between vehicles for the entire column.
 - (4) March unit. Composed of vehicle(s) and vehicle interval(s).
- (5, March unit interval. The distance (in kilometers) between march units.
 - (6) Serial. Composed of march unit(s) and march unit interval(s).
 - (7) Serial interval. The distance (in kilometers) between serials.
- (8) Column. The entire force. It is composed of serial(s) and serial interval(s).
 - (9) Halts. Stops (in minutes) at particular checkpoints.
 - (10) Route. Composed of road segments.
 - (11) Road segment. Has the attributes of distance and rate of travel.
- b. Model Application. MOVEPLAN is an automated tool which was designed to assist movement planners to develop a movement table. A primary source of doctrinal information which was used during MOVEPLAN development was FM 55-30, Army Motor Transport Units and Operations. Most movement planning doctrine and "schoolhouse" procedures are taught with a fundamental assumption: constant pace or rate of march. While this assumption is acceptable for administrative moves, it is not appropriate for tactical movement across different types of roads and cross-country terrain under both day and limited visibility conditions. Consideration of varying movement rates over a route was a principal factor in the design of MOVEPLAN. As a result, the effects of queueing or backup along the route are represented in MOVEPLAN.

c. Model Capabilities and Limitations.

(1) Capabilities.

- (a) Handles up to 10 serials with 10 march units in each serial.
- (b) Handles a single route with up to 20 road segments.
- (c) Provides a capability for rest/refueling halts for all units at specific checkpoints.
 - (d) Provides a capability to limit speeds on each road segment.
- (e) Provides a capability to plan movement under three alternative march disciplines, described below.
- 1. Hasty with fixed start intervals: Each march unit travels as rapidly as conditions will allow but does not pass units ahead of it. Each march unit starts at a fixed interval behind the unit ahead of it.
- 2. Hasty with staggered starts: Each march unit travels as rapidly as conditions will allow but does not pass units ahead of it. Starts are staggered automatically to eliminate coagestion on the route.
- 3. Control move: Force/march column integrity is maintained. Units start at fixed intervals. Slowest movement condition affecting the force dictates the force march rate.
- (f) Provides a pace for each march unit for each road segment as a guideline for the pace vehicle and for the movement planner.
- (g) Computes the average speed for the lead march unit across the route.
- (h) Computes the (static) column length and (static) vehicle density.
- (i) Computes due-in and release time for each march unit for each checkpoint.
 - (j) Summarizes the movement by serial.
 - (k) Summarizes the route description.
- (2) Limitations. Currently, MOVEPLAN is restrictive in the following areas:
- (a) Does not handle multiple start points (SP) or multiple release points (RP).
 - (b) All march units must occupy designated rest/refueling halts.
- (c) Does not allow for a variable maximum pace for each type unit (wheeled vs tracked vs mixed vehicle units).
- (d) Does not consider oversize or overweight vehicles and route limitations.

- (e) Does not deal with transition conditions (day to night).
- (f) Does not perform route selection or analysis tasks.
- (g) Does not perform tactical movement planning on a multiple-route network, since it is a single-route processing model.

COMPRESSION STREET, WORKER BOWERS DOWNSON

- d. <u>Model Operation</u>. MOVEPLAN may be used by U.S. Army tactical movement planners at levels from section to corps. MOVEPLAN inputs are obtained from map inspection, subordinate unit reports, and unit tactical standing operating procedures (TSOP's). MOVEPLAN outputs are used by the movement planners and are an enclosure to the Movement Annex of an OPORD or a Letter of Instruction to subordinate units.
- e. <u>Model Configuration</u>. This program is designed for an IBM or compatible microcomputer w/CRT, a disk drive, and a printer. Components include the MOVEPLAN (1.0) Users Manual and the 5 1/4-inch diskette, MOVEPLAN (1.0).
- f. Model Organization. MOVEPLAN is an interactive software application. MOVEPLAN's oftware components are primarily an input routine, a computation routine, an output routine, and help and file maintenance routines. The software is driven by user-selected menu options and creation or recall of data files on units and routes.




Figure 1. MOVEPLAN organization





Figure 2. Input routine



general secretors especies especies especies mecanica representa terrescent

Figure 3. Calculation routine




Figure 4. Output routine

- g. Performance. MOVEPLAN is a responsive software application that provides relational movement information. Input intensity is highly dependent on the number of route segments and march units in the force. Response time is less than 5 minutes for an average-size force on a route with less than six different route segments.
- h. <u>Data Base</u>. The MOVEPLAN data base consists solely of the executable programs and user created movement files. As a stand-alone application, MOVEPLAN does not access files from other automated sources or systems. Definitions of MOVEPLAN data elements are provided in section 2a.

i. General Description of Inputs, Processing, Outputs.

See Best Areas Consider the See Constant Constan

- (1) Inputs. MOVEPLAN (1.0) requires information to be provided by Army tactical movement planners in the order shown on the sample data input sheet in appendix A. This information consists of data file name, maximum pace, vehicle interval, average vehicle length, march unit interval, serial interval, route name, number of road segments in the route, segment maximum rates and distances, number of serials, serial names, number of march units in each serial, march unit names, number of vehicles in each march unit, halt times at each checkpoint and release point, choice of march discipline, desired arrival or start time, and number of days to departure.
- (2) Processing. Once inputs are completed, lengths of segments and movement rates on segments are established for the route. March unit lengths are computed and rest areas are established for the route. Due and clear times at each checkpoint are computed for each march unit and conflicts at checkpoints are resolved. Times are adjusted for user-defined arrival or start. The program is then ready to produce outputs.
- (3) Outputs. MOVEPLAN (1.0) produces a road movement table, a column analysis of pass times, and a description of the route in terms of lengths and travel rates. See appendix D for sample outputs from MOVEPLAN (1.0).

3. TECHNICAL OPERATIONS.

- a. <u>Initiation Procedures</u>. This section will get the user started and ready to use MOVEPLAN. The writers assume the user has some experience with computers and has reviewed the computer's operating instructions.
 - (1) In order to begin, the user will need the following:
 - (a) IBM PC or compatible microcomputer with disk drive.
 - (b) IBM-compatible printer.
 - (c) System (PC-DOS or MS-DOS) and MOVEPLAN diskettes.
 - (d) MOVEPLAN (1.0) Users Manual.
 - (2) To start and load the computer, the user must do the following:
 - (a) Turn on the computer and printer.
- (b) Load the PC-DOS or MS-DOS system according to the computer's operating instructions.
- (c) Insert the MOVEPLAN diskette in the drive, type MOVEPLAN, and press the [ENTER] key. The program should load, and the main menu should appear on the screen (figure 5).

MOVEPLAN (1.0)
A UNIT MOVEMENT PLANNING AID
COMMAND CONTROL ANALYSIS DIVISION
USACAORA
FT LEAVENWORTH, KANSAS 66027
AUTOVON 552-4309

The following choices can be made from the main menu:

- 1. RUN PROBLEM
- 2. GENERAL PROGRAM INFORMATION
- 3. QUIT

WHI PROCESS STATES EXPERIES SERVICES SERVICES SERVICES BESTERES SOUTHE SERVICES SERVICES

- 4. READ DATA FROM DISK FILE
- 5. SAVE DATA TO DISK FILE
- 6. INPUT OR CHANGE DATA
- 7. GET DATA INPUT SHEET
- 8. DELETE A DATA FILE
- 9. LISTING OF FILES

ENTER 1,2,3,4,5,6,7,8,0R 9

Figure 5. Title and main menu screen

- b. <u>Tutorial</u>. The purposes of this program are best served by guiding the user through a tutorial session. A data input sheet will be printed out so that the user may compile the input data. Then the data will be keyed into the computer, saved to a data file, and the data will be computed and printed out in a report. Next, the user will make changes to the data file, another report will be printed reflecting the new results, and the session will be ended. Instructions for deleting and listing files will also be provided.
 - (1) Completing a Data Input Sheet.

MOVEPLAN (1.0)
A UNIT MOVEMENT PLANNING AID
COMMAND CONTROL ANALYSIS DIVISION
USACAORA
FT LEAVENWORTH, KANSAS 66027
AUTOVON 552-4309

The following choices can be made from the main menu:

- 1. RUN PROBLEM
- 2. GENERAL PROGRAM INFORMATION
- 3. QUIT

THE RESIDENCE CONTRACT STREET, SECURITY SECURITY SECURITY

- READ DATA FROM DISK FILE
- 5. SAVE DATA TO DISK FILE
- 6. INPUT OR CHANGE DATA
- 7. GET DATA INPUT SHEET
- 8. DELETE A DATA FILE
- 9. LISTING OF FILES

ENTER 1,2,3,4,5,6,7,8,0R 9

Figure 5. Title and main menu screen

Step 1: Assuming that the steps in the Initiation Procedures section were done correctly, the title and main menu (figure 5) should be on the screen. Enter 7 (by typing 7 and pressing the [ENTER] key) to print out a data input sheet (see figure 6, Sample data input sheet with sample data).

Step 2: After the data input sheet is printed, the main menu will reappear. Enter 2 in order to obtain instructions on completing the data input sheet. Follow each step, copying onto the data input sheet the data from the example input sheet, figure 6. Figure 7 lists the general program instructions. After completing this step, the movement rate guidelines, based on \underline{FM} 7-20, The Infantry Battalion, will appear on the screen (figure 8).

DATA FILE RAME THUE MAX PACE 35 KMPH VEHICLE INTERVAL 50 METERS AVG VEHICLE LENGTH 8 METERS MARCH UNIT INTERVAL 3 KM SERIAL INTERVAL 5 KM					
NUMBER OF ROAD SEGMENTS IN ROUTE 5					
SEGMENT	MAX RATE(KMPH)	DISTANCE(KM)	SEGMENT	MAX RATE(KMPH)	DISTANCE (KM)
1 2 3 4 5 6 7 8 9 10	35 30 35 20 35 	22 24 22 10 44	11 12 13 14 15 16 17 18 19		
SERIAL # SERIAL NA # OF MAR		4 MU NAME A/4-77 HHC/4-77 B/4-77 E/4-77	SERIAL SERIAL BOF H MU 1 2 3 4 5 6 7 8 9	NAME 1BDE CS MARCH UNITS IN SE POF VEHICLES 195 72 50	RIAL 3 MU NAME 4-40 FA A/4-441 AD A/55 EN
OF MAR	2 AME TF4-2 CH UNITS IN SERIAL OF VEHICLES 21 36 27 19	4 HIT NAME B/4-2 HHC/4-2 E/4-2 A/4-2		L NAME 18DE FS8 MARCH UNITS IN SI # OF VEHICLES 156	MU NAME 1BOE FSB
CP HALT TIME (MINS) CP HALT TIME (MINS) SP					
NUMBER OF DAYS TO DEPARTUREO					

Figure 6. Sample data input sheet with sample data

GENERAL PROGRAM INFORMATION

STEP ONE-DETERMINE GENERAL INFORMATION AND SERIAL CONSTANTS

LIST ON THE INPUT SHEET THE FOLLOWING:

DATA FILE NAME (FOR EXAMPLE: 3BDE9ID)

MAXIMUM SPEED FOR SLOWEST VEHICLE (MAX PACE)

VEHICLE INTERVAL IN METERS (999 METERS MAXIMUM)

AVERAGE VEHICLE LENGTH IN METERS (99 METERS MAXIMUM)

MARCH UNIT INTERVAL IN KILOMETERS (999 KILOMETERS MAXIMUM)

SERIAL INTERVAL IN KILOMETERS (999 KILOMETERS MAXIMUM)

PRESS ENTER TO CONTINUE

SCHOOLS STATEMENT DOTTOTAL SECURITY CONTROL

STEP TWO-ORGANIZE ROUTE INFORMATION

LIST ON I.. DATA INPUT SHEET THE ROUTE NAME, THE NUMBER OF ROAD SEGMENTS IN THE ROUTE, AND FOR EACH ROAD SEGMENT, THE MAXIMUM TRAVEL RATE AND THE DISTANCE.

PRESS ENTER TO CONTINUE

STEP THREE-ORGANIZE SERIAL INFORMATION

LIST ON THE DATA INPUT SHEET THE NUMBER OF SERIALS. FOR EACH SERIAL, LIST THE SERIAL NAME AND THE NUMBER OF MARCH UNITS IN THE SERIAL. FOR EACH MARCH UNIT, ENTER THE NUMBER OF VEHICLES AND THE MARCH UNIT NAME.

PRESS ENTER TO CONTINUE

STEP FOUR-DETERMINE HALT TIMES

LIST ON THE DATA INPUT SHEET ANY HALT TIMES AT CHECKPOINTS. HALT TIME CANNOT BE ENTERED AT THE START POINT (SP).

STEP FIVE-DETERMINE MARCH DISCIPLINE AND TIME CONSTANTS

INDICATE ON THE DATA INPUT SHEET THE DESIRED MARCH DISCIPLINE, DESIRED ARRIVAL TIME OR DESIRED START TIME, AND NUMBER OF DAYS TO DEPARTURE.

PRESS ENTER TO CONTINUE

Figure 7. General program information

MOVEMENT RATE GUIDE (UNOPPOSED) (KMPH)

CONTROL CONTROL CONTROLS CONTROLS

WEATHER CONDITION (DAY/N-LIGHTS/N-BLACKOUT)

			(DAI/M-FIGUIO/M-0FV	NOU I)
			LIGHT	FOG/HVY
TERRAIN	UNIT TYPE	GOOD	PRECIPITATION	PRECIPITATION
ROAD	FOOT TRPS	4/3.2/3.2	3.2/2.5/2.5	2.4/1.9/1.9
KUND	TRK, GENRL	40/40/16	32/32/12.8	24/24/9.6
	TRCKD VEH	24/24/16	16.8/16.8/11.2	12/12/8
	ARTY, TRCK	40/40/16	32/32/16	24/24/9.6
	ARTY, TRCTR	32/32/16	22.4/22.4/11.2	16/16/8
X-COUNTRY	FOOT TRPS	2.4/1.6/1.6	1.9/1.2/1.2	1.4/0.9/0.9
X-COUNTRY	TRK.GENRL	12/8/8	9.6/6.4/6.4	7.2/4.8/4.8
	TRCKD VEH	16/8/8	11.2/5.6/5.6	8/4/4
	ARTY, TRCK	12/8/8	9.6/6.4/6.4	7 <i>.</i> 2/4.8/4.8
	ARTY, TRCTR	16/8/8	11.2/5.6/5.6	8/4/4

Figure 8. Movement rate guidelines1.

These movement rate guidelines are based on \underline{FM} 7-20, The Infantry Battalion.

(2) Entering Data and Saving the Data to a File.

Step 1: At the conclusion of general program information, the main menu will reappear. Enter 6 to input data from the data input sheet. Prompts will appear on the screen, requesting the same information as recorded on the input sheet and in the same order as the information on the input sheet. Enter each data item as required. See appendix B for a list of those prompts, together with responses for the example problem.

Step 2: After the data have been entered, the main menu will reappear. At this point, the user may review his data by entering 6, run the problem using his data by entering 1, or save his data to a disk file by entering 5. If the data are not saved to a file, they will not be permanently stored, and once the program is exited, the data will be lost. Therefore, the user is encouraged to enter 5 and save the data to a file. The user is asked to name a file for the data. Enter IBDE for this example, as shown at the top of the data input sheet, figure 6.

FILE TO WRITE DATA TO? | 1BDE [ENTER]

(3) Step 3: Once again the main menu will appear. Enter 6 to review the data in IBDE. Changes or corrections may be made at this time.

MAX PACE = 35
ENTER THE MAX PACE (MAX SPEED OF SLOWEST VEH.) [ENTER]

(3) Running the Problem.

RESEL TRANSPORT BERNARD CONTRACTOR RELEGIONS SECTION SECTIONS. VINNERS.

Step 1: After the data have been reviewed, the main menu will reappear. Enter 1 to run the problem. The program will then ask for the information at the bottom of the data input sheet. The march discipline menu will appear. Enter 2 for this example, according to the data input sheet.

RESULTS FROM WHICH MARCH DISCIPLINE?

- 1. HASTY WITH FIXED START INTERVALS
- 2. HASTY WITH STAGGERED STARTS
- CONTROL MOVE

ENTER 1 OR 2 OR 3 OR 4 (TO RETURN TO MAIN MENU) 2 [ENTER]

The program will then show the time required for the move and ask the user to choose a desired arrival or start time. Enter 2 according to the data input sheet.

THE MOVE TAKES 7 HOURS AND 28 MINUTES

OPTIONS

- [1] SPECIFY A DESIRED ARRIVAL TIME (ARRIVAL OF FIRST VEHICLE AT RP)
- [2] SPECIFY A DESIRED START TIME (START OF FIRST VEHICLE FROM SP)
- [3] RETURN TO MAIN MENU

ENTER 1, 2, OR 3

2 [ENTER]

The program will ask for the desired start time. Enter 0700 for this example.

ENTER THE DESIRED START TIME OF LEAD VEHICLE IN MILITARY CLOCK ? 0700 [ENTER]

Lastly, the program will ask the user to indicate the number of days to departure. Enter O according to the data input sheet.

ENTER THE NUMBER OF DAYS FROM TODAY TO DEPARTURE (e.g. ENTER 2 FOR THE DAY AFTER TOMORROW)
? 0 [ENTER]

The program will immediately begin to run, and the printer will immediately begin to print the output consisting of a road movement table, time analysis, and route description on separate pages. See appendix D for output from the example, 1BDE.

Step 2: Before the printer has finished printing, the main menu will reappear on the screen. The user may now run another problem by changing the data (choice 6) or may quit (choice 3).

(4) Changing the Data File.

Step 1: If the user wishes to make changes to the data file, and if he has not exited the program, he should enter 6 from the main menu. If the user has exited the program and is restarting the program, he needs to enter MOVEPLAN, then enter 4 to read data from a disk file. When prompted for the file name, he should enter 1BDE.

FILE NAME? 1BDE [ENTER]

The main menu will then appear, and the user should enter 6. As the data is reviewed, anges may be made. As an example, the following changes to IBDE will be made: a serial will be added, consisting of four march units, and the halt time at checkpoint 3 will be removed. See appendix C for a listing of prompts and responses for the sample changes to 1 BDE.

Step 2: At the conclusion of choice 6, the main menu will reappear. The user may enter 6 to review his changes, enter 5 to save the data to a disk file (either IBDE, in which case the new data will replace the old data, or a new name, such as IBDE(2) to save the new data as well as the old data in separate files), or enter 1 to run the problem.

(5) Running the New Problem and Ending the Session.

Step 1: The user should respond to the prompts for choice I exactly as he did for IBDE, since none of that information was changed. Enter 2 for the march discipline, enter 2 for the desired start time, enter 0700 for the time itself, and enter 0 for the number of days to departure. Once again, the program will print a road movement table, time analysis, and route description. The user may compare the outputs of the two example problems.

Step 2: To end the session, simply enter 3, quit.

(6) Deleting a Data File.

CONTROL SECTION DESCRIBE DESCRIBE SECTION SECTION VERSION SECTION SECTION SECTION

Step 1: From the main menu, enter 8. The program will ask the user which file he wants to delete.

FILE TO ERASE name of file [ENTER]

Step 2: Enter the name of the file to be deleted. At the conclusion of this step the program will state that the file is erased and will return the main menu.

(7) Listing of Files.

Step 1: To see the list of files on the diskette, enter 9 from the main menu. Press the [ENTER] key again to obtain the default directory. (If another directory is desired, enter the path specification indicated in the machine's MS-DOS manual.) The MOVEPLAN (1.0) diskette is distributed with five files on it, so the user should see those files (shown in fig. 9) plus any others he has added.

; -	MOVEPLAN.EXE	DATA. IPS	HELP.MOV	DEM0	
i	IBDE				1

Figure 9. Input prompt for choice 9, listing of files.

An explanation of the contents of the five original files follows:

- (a) MOVEPLAN.EXE This is the executable program for MOVEPLAN (1.0). (DO NOT DELETE THIS FILE.)
- (b) DATA.IPS and HELP.MOV These are both text files used by MOVEPLAN (1.0). (DO NOT DELETE THESE FILES.)
- (c) DEMO and 1BDE Each of these is the data file for the example 1BDE in the MOVEPLAN (1.0) Users Manual. They are identical except for file name. If the user wishes to run an example problem right away, he can enter 4 to read the data from DEMO or 1BDE and then enter 1 to run it. He will still have to enter the information from the bottom of the example data input sheet (figure 6 or appendix A), beginning with the choice of march discipline, in order to run DEMO or 1BDE. If he follows this tutorial step by step, he will actually re-create 1BDE.
 - Step 2: Press [ENTER] to return to the main menu.
- c. Utilization of Model Outputs. The MOVEPLAN outputs are utilized by the following personnel in the indicated manner:
- (1) Transportation Planner. Uses outputs to make adjustments to detailed movement plan and uses outputs as a control schedule during movement of the force.
- (2) Movement Control Teams. Use outputs as a reference for making decisions about unit priorities along the route of march when conflicts occur.

- (3) March Unit and Serial Commanders. Use outputs as a reference to execute move both in terms of start time and pace on each route segment.
- (4) Force Commander. Uses outputs as an estimate of time and location of units as the march progresses.
- d. Recovery and Error Correction Procedures. MOVEPLAN (1.0) provides the error messages shown in table 1. In all but one case, MOVEPLAN allows the user to correct the error and continue the program with the message PRESS ENTER TO CONTINUE. In the event that an I/O error occurs on a disk I/O operation, the system cannot recover from the error. The message DEVICE I/O ERROR will appear, and the user will have to restart the system according to the instructions given in section 3a of this manual. If the user enters incorrect data, it is best to complete the data input and then review or change the data using choice 6 from the main menu. Otherwise, he may use the [Control] [Break] keys to restart the program, but he will lose his data. To restart the program, he should type in MOVEPLAN.

Table 1. MOVEPLAN error messages

ERROR MESSAGE

١.	DEVICE TIMEOUT	PRINTER NOT CONNECTED TO COMPUTER
2.	DEVICE FAULT	PRINTER NOT ON LINE
3.	OUT OF PAPER	
4.	FILE NOT FOUND	
5.	DEVICE I/O ERROR	DISK DRIVE OR DISKETTE DAMAGED
6.	BAD FILE NAME	
7.	DEVICE UNAVAILABLE	DISK DRIVE NOT PROPERLY CLOSED
8.	DISK WRITE PROTECTED	
9.	DISK NOT READY. (NOT IN DRIVE?)	
10.	DISK MEDIA ERROR	DISK DRIVE OR DISKETTE NOT WORKING
		PROPERLY

POSSIBLE CAUSE

4. SUMMARY.

]

OPEN PROVINCE AND SECTION SECTIONS AND SECURIORS

a. General. MOVEPLAN is a flexible, responsive, transparent software application which significantly reduces the time and error associated with tactical movement planning. The user should work through the tutorial and re-read this document to ensure understanding of MOVEPLAN operations, capabilities, and limitations.

11. PATH/FILE ACCESS ERROR PATH NAME ENTERED INCORRECTLY

b. Assistance. Questions concerning MOVEPLAN (1.0) should be directed to:

Commander
USACAORA
ATTN: ATOR-CAS-CF
Ft. Leavenworth, KS 66027-5220
AV 552-4309 COMM (913) 684-4309

c. Obtaining MOVEPLAN (1.0). MOVEPLAN (1.0) will be released through the Command and Control Microcomputer Users Group (C2MUG) at Fort Leavenworth, KS, in May 1986. Requests for the MOVEPLAN (1.0) diskette and Users Manual may be directed to:

Chief, CECOM ATTN: AMSEL-FL-SDSD (C2MUG) Ft. Leavenworth, KS 66027-5600

terester secretary because a secretary popular

(THIS PAGE INTENTIONALLY LEFT BLANK)

APPENDIX A

DATA INPUT SHEET AND SAMPLE DATA

NUMBER O	ME Blue F ROAD SEGMENTS I				
SEGMENT	MAX RATE(KMPH)	DISTANCE(KM)	SEGMENT	MAX RATE(KMPH)	DISTANCE(K
1 2 3 4 5 6 7 8	35 30 35 20 35	22 24 22 10 44	11 12 13 14 15 16 17		
9 10	F SERIALS 4		19 20		
# OF MAR	AME TF4-77 CH UNITS IN SERIAL OF VEHICLES 28 42 23 32	4 MU NAME A/4-77 HHC/4-77 B/4-77 C/4-77		MME CH UNITS IN SERIA DF VEHICLES M	NAME
SERIAL NA # OF MAR(WE TF4-2 CH UNITS IN SERIAL DF VEHICLES 21 36 27 19	MU NAME B/4-2 HHC/4-2 C/4-2 A/4-2	SERIAL NA # OF MARC	ME CH UNITS IN SERIA	L U NAME

SERIAL # 3		SERIAL # 8	
SERIAL NAME 1BDE CS		SERIAL NAME	
# OF MARCH UNITS IN SERIAL	3	# OF MARCH UNIT	S IN SERIAL
MU # OF VEHICLES	MU NAME	MU # OF VEHI	CLES MU NAME
1 195	4-40 FA	1	
2 72	A/4-441 AD	2	
3 50	A/55 EN	3	
4		4	
5		5	
6		6	
7		7	
8		8	-
9	***********	9	
			
10		10	
0.00		0.00.00.00.00.00	
SERIAL # 4		SERIAL # 9	
SERIAL NAME 1BDE FSB		SERIAL NAME	
# OF MARCH UNITS IN SERIAL	1	# OF MARCH UNIT	TS IN SERIAL
MU # OF VEHICLES	MU NAME	MU # OF VEHIC	CLES MU NAME
1 156	1BDE FSB	1	
2		2	-
3		3	
4		4	-
5	******	5	
6		6	
7		7	-
8		8	
9		ğ	
10		10	
			-
SERIAL # 5		SERIAL # 10	
SERIAL NAME		SERIAL NAME	
# OF MARCH UNITS IN SERIAL		# OF MARCH UNITS	TH CEDIAL
	MU NAME		
MU # OF VEHICLES	MU NAME	MU # OF VEHIC	CLES MU NAME
1		1	•
2		2	•
			-
4		4	
5		5	
6		6	
7		7	
8		8	
9		9	
10		10	
			

CP	HALT TIME(MINS)	CP	HALT TIME(MINS)	CP	HALT TIME(MINS)
SP	***	7		14	
1	0	8		15	
2	0	9	**************************************	16	
3	30	10		17	_
Δ		11	*************************************	18	-
5		12		19	
6		13		R D	
U	-	1.5		IXF	

RESULTS FROM WHICH MARCH DISCIPLINE (CIRCLE ONE)

- 1. HASTY WITH FIXED START INTERVALS
 ASTY WITH STAGGERED STARTS
 CONTROL MOVE

Present assessed franceae arrange areases assessed assessed assessed assessed

DESIRED ARRIVAL TIME (FIRST VEHICLE AT RP) DESIRED START TIME (FIRST VEHICLE AT SP) 0700 NUMBER OF DAYS TO DEPARTURE _ O___

(THIS PAGE INTENTIONALLY LEFT BLANK)

LYMPH TO THE SECOND SECOND SECOND CONTROL OF THE PROPERTY OF

APPENDIX B

DATA INPUT PROMPTS AND SAMPLE RESPONSES

SYSTEM: ENTER THE MAX PACE (MAX SPEED OF SLOWEST VEH.)

USER: 3

SYSTEM: ENTER VEHICLE INTERVAL IN METERS

USER: 50

SYSTEM: ENTER AVG VEH LENGTH IN METERS

USER: 8

SYSTEM: ENTER MARCH UNIT INTERVAL IN KM

USER:

SYSTEM: ENTER SERIAL INTERVAL IN KM

USER:

SYSTEM: ENTER ROUTE NAME, 10 CHARACTERS OR LESS

USER: Blue

SYSTEM: ENTER # OF SEGMENTS, MAX 20

USER:

SYSTEM: THIS IS SEGMENT NO. 1

ENTER MAX SPEED IN KMPH

USER: 35

SYSTEM: ENTER DISTANCE IN KM

USER: 2

SYSTEM: THIS IS SEGMENT NO. 2

ENTER MAX SPEED IN KMPH

USER: 3

SYSTEM: ENTER DISTANCE IN KM

USER: 24

SYSTEM: THIS IS SEGMENT NO. 3

ENTER MAX SPEED IN KMPH

USER: 3

SYSTEM: ENTER DISTANCE IN KM

USER: 22

SYSTEM: THIS IS SEGMENT NO. 4

ENTER MAX SPEED IN KMPH

USER: 20

SYSTEM: ENTER DISTANCE IN KM

USER: 10

SYSTEM: THIS IS SEGMENT NO. 5

ENTER MAX SPEED IN KMPH

USER: 35

SYSTEM: ENTER DISTANCE IN KM

USER: 44

SYSTEM: ENTER NO. OF SERIALS (MAX 10)

USER:

METERICAL ESCRIPTION OF PROPERTY STREET, STREET,

SYSTEM: THIS IS SERIAL NO. 1

ENTER SERIAL NAME, 10 CHARACTERS OR LESS

USER: TF4-77

SYSTEM: ENTER # OF MARCH UNITS (MAX 10)

USER: 4

SYSTEM: IN SERIAL NO. 1 THIS IS MARCH UNIT NO. 1

ENTER # OF VEHS. IN MU

USER: 28

SYSTEM: ENTER MARCH UNIT NAME, 10 CHARACTERS OR LESS

USER: A/4-77

SYSTEM: IN SERIAL NO. 1 THIS IS MARCH UNIT NO. 2

ENTER # OF VEHS. IN MU

USER: 42

SYSTEM: ENTER MARCH UNIT NAME, 10 CHARACTERS OR LESS

USER: HHC/4-77

SYSTEM: IN SERIAL NO. 1 THIS MARCH UNIT NO. 3

ENTER # OF VEHS. IN MU

USER: 23

SYSTEM: ENTER MARCH UNIT NAME, 10 CHARACTERS OR LESS

USER: B/4-77

SYSTEM: IN SERIAL NO. 1 THIS IS MARCH UNIT No. 4

ENTER # OF VEHS. IN MU

USER: 32

SYSTEM: ENTER MARCH UNIT NAME, 10 CHARACTERS OR LESS

USER: C/4-77

SYSTEM: THIS IS SERIAL NO. 2

ENTER SERIAL NAME, 10 CHARACTERS OR LESS

USER: TF4-2

SYSTEM: ENTER # OF MARCH UNITS (MAX 10)

USER:

SYSTEM: IN SERIAL NO. 2 THIS IS MARCH UNIT NO. 1

ENTER # OF VEHS. IN MU

USER:

SYSTEM: ENTER MARCH UNIT NAME, 10 CHARACTERS OR LESS

USER: B/4-2

SYSTEM: IN SERIAL NO.2 THIS IS MARCH UNIT NO. 2

ENTER # OF VEHS. IN MU

USER: 36

SYSTEM: ENTER MARCH UNIT NAME, 10 CHARACTERS OR LESS

USER: HHC/4-2

SYSTEM: IN SERIAL NO. 2 THIS IS MARCH UNIT NO. 3

ENTER # OF VEHS. IN MU

USER: 27

SYSTEM: ENTER MARCH UNIT NAME, 10 CHARACTERS OR LESS

USER: C/4-2

SYSTEM: IN SERIAL NO. 2 THIS IS MARCH UNIT NO. 4

ENTER # OF VEHS. IN MU

USER: 19

SYSTEM: ENTER MARCH UNIT NAME, 10 CHARACTERS OR LESS

USER: A/4-2

SYSTEM: THIS IS SERIAL NO. 3

ENTER SERIAL NAME, 10 CHARACTERS OR LESS

USER: 1BDE CS

SYSTEM: ENTER # OF MARCH UNITS (MAX 10)

USER: 3

SYSTEM: IN SERIAL NO. 3 THIS IS MARCH UNIT NO. 1

ENTER # OF VEHS. IN MU

USER: 195

SYSTEM: ENTER MARCH UNIT NAME, 10 CHARACTERS OR LESS

USER: 4-40 FA

SYSTEM: IN SERIAL NO. 3 THIS IS MARCH UNIT NO. 2

ENTER # OF VEHS. IN MU

USER: 72

SYSTEM: ENTER MARCH UNIT NAME, 10 CHARACTERS OR LESS

USER: A/4-441 AD

SYSTEM: IN SERIAL NO. 3 THIS IS MARCH UNIT NO. 3

ENTER # OF VEHS. IN MU

USER: 50

SYSTEM: ENTER MARCH UNIT NAME, 10 CHARACTERS OR LESS

USER: A/55 EN

SYSTEM: THIS IS SERIAL NO. 4

ENTER SERIAL NAME, 10 CHARACTERS OR LESS

USER: 18DE FS8

SYSTEM: ENTER # OF MARCH UNITS (MAX 10)

USER:

SYSTEM: IN SERIAL NO. 4 THIS IS MARCH UNIT NO. 1

ENTER # OF VEHS. IN MU

USER: 156

SYSTEM: ENTER MARCH UNIT NAME, 10 CHARACTERS OR LESS

USER: 1BDE FSB

SYSTEM: THIS IS CHECKPOINT 1

ENTER HALT TIME IN MINUTES

USER:

SYSTEM: THIS IS CHECKPOINT 2

ENTER HALT TIME IN MINUTES

USER:

SYSTEM: THIS IS CHECKPOINT 3

ENTER HALT TIME IN MINUTES

USER: 30

SYSTEM: THIS IS CHECKPOINT 4

ENTER HALT TIME IN MINUTES

USER:

SYSTEM: THIS IS CHECKPOINT RP

ENTER HALT TIME IN MINUTES

USER: (

APPENDIX C

CHANGE DATA PROMPTS AND SAMPLE RESPONSES

SYSTEM: MAX PACE = 35

ENTER THE MAX PACE (MAX SPEED OF SLOWEST VEH.)

USER: [ENTER]

SYSTEM: VEHICLE INTERVAL 50

ENTER VEHICLE INTERVAL IN METERS

USER: [ENTER]

SYSTEM: AVG VEHICLE LENGTH 8

ENTER AVG VEH LENGTH IN METERS

USER: [ENTER]

SYSTEM: MARCH UNIT INTERVAL = 3

ENTER MARCH UNIT INTERVAL IN KM

USER: [ENTER]

SYSTEM: SERIAL INTERVAL IN KM = 5

ENTER SERIAL INTERVAL IN KM

USER: [ENTER]

SYSTEM: ROUTE NAME = Blue

ENTER ROUTE NAME, 10 CHARACTERS OR LESS

USER: [ENTER]

SYSTEM: NUMBER OF ROAD SEGMENTS = 5

ENTER # OF SEGMENTS, MAX 20

USER: [ENTER]

SYSTEM: THIS IS SEGMENT NO. 1

SPEED = 35

ENTER MAX SPEED IN KMPH

USER: [ENTER]

SYSTEM: DISTANCE = 22

ENTER DISTANCE IN KM

USER: [ENTER]

SYSTEM: THIS IS SEGMENT NO. 2

SPEED = 30

ENTER MAX SPEED IN KMPH

USER: [ENTER]

SYSTEM: DISTANCE = 24

ENTER DISTANCE IN KM

SYSTEM: THIS IS SEGMENT NO. 3

SPEED = 35

ENTER MAX SPEED IN KMPH

USER: [ENTER]

SYSTEM: DISTANCE = 22

ENTER DISTANCE IN KM

USER: [ENTER]

SYSTEM: THIS IS SEGMENT NO. 4

SPEED = 20

ENTER MAX SPEED IN KMPH

USER: [ENTER]

SYSTEM: DISTANCE = 10

ENTER DISTANCE IN KM

USER: [ENTER]

SYSTEM: THIS IS SEGMENT NO. 5

SFLID = 35

ENTER MAX SPEED IN KMPH

USER: [ENTER]

SYSTEM: DISTANCE = 44

ENTER DISTANCE IN KM

USER: [ENTER]

SYSTEM: NUMBER OF SERIALS = 4

ENTER NO. OF SERIALS (MAX 10)

USER:

SYSTEM: THIS IS SERIAL NO. 1

SERIAL NAME = TF4-77

ENTER SERIAL NAME, 10 CHARACTERS OR LESS

USER: [ENTER]

SYSTEM: # OF MARCH UNITS = 4

ENTER # OF MARCH UNITS (MAX 10)

USER: [ENTER]

SYSTEM: IN SERIAL NO. 1 THIS IS MARCH UNIT NO. 1

OF VEHICLES IN MU = 28 ENTER # OF VEHS. IN MU

USER: [ENTER]

SYSTEM: MARCH UNIT NAME = A/4-77

ENTER MARCH UNIT NAME, 10 CHARACTERS OR LESS

SYSTEM: IN SERIAL NO. 1 THIS IS MARCH UNIT NO. 2

OF VEHICLES IN MU = 42 ENTER # OF VEHS. IN MU

USER: [ENTER]

SYSTEM: MARCH UNIT NAME = HHC/4-77

ENTER MARCH UNIT NAME, 10 CHARACTERS OR LESS

USER: [ENTER]

SYSTEM: IN SERIAL NO. 1 THIS IS MARCH UNIT NO. 3

OF VEHICLES IN MU = 23 ENTER # OF VEHS. IN MU

USER: [ENTER]

SYSTEM: MARCH UNIT NAME = B/4-77

ENTER MARCH UNIT NAME, 10 CHARACTERS OR LESS

USER: [ENTER]

SYSTEM: IN SERIAL NO. 1 THIS IS MARCH UNIT NO. 4

OF VEHICLES IN MU = 32 ENTER # OF VEHS. IN MU

USER: [ENTER]

SYSTEM: MARCH UNIT NAME = C/4-77

ENTER MARCH UNIT NAME, 10 CHARACTERS OR LESS

USER: [ENTER]

SYSTEM: THIS IS SERIAL NO. 2

SERIAL NAME = TF4-2

ENTER SERIAL NAME, 10 CHARACTERS OR LESS

USER: [ENTER]

SYSTEM: # OF MARCH UNITS = 4

ENTER # OF MARCH UNITS (MAX 10)

USER: [ENTER]

SYSTEM: IN SERIAL NO. 2 THIS IS MARCH UNIT NO. 1

OF VEHICLES IN MU = 21 ENTER # OF VEHS. IN MU

USER: [ENTER]

SYSTEM: MARCH UNIT NAME = B/4-2

ENTER MARCH UNIT NAME, 10 CHARACTERS OR LESS

USER: [ENTER]

SYSTEM: IN SERIAL NO. 2 THIS IS MARCH UNIT NO. 2

OF VEHICLES IN MU = 36 ENTER # OF VEHS. IN MU

USER: [ENTER]

SYSTEM: MARCH UNIT NAME = HHC/4-2

ENTER MARCH UNIT NAME, 10 CHARACTERS OR LESS

SYSTEM: IN SERIAL NO. 2 THIS IS MARCH UNIT NO. 3

OF VEHICLES IN MU = 27 ENTER # OF VEHS. IN MU

USER: [ENTER]

SYSTEM: MARCH UNIT NAME = C/4-2

ENTER MARCH UNIT NAME, 10 CHARACTERS OR LESS

USER: [ENTER]

BACCASAS CACACAS SASSASSA

STATESTAL SECRETARY SERVICES SECRETARY SECRETARY

SYSTEM: IN SERIAL NO. 2 THIS IS MARCH UNIT NO. 4

OF VEHICLES IN MU = 19 ENTER # OF VEHS. IN MU

USER: [ENTER]

SYSTEM: MARCH UNIT NAME = A/4-2

ENTER MARCH UNIT NAME, 10 CHARACTERS OR LESS

USER: [ENTER]

SYSTEM: THIS IS SERIAL NO. 3
SERIAL NAME = 1BDE CS

NTER SERIAL NAME, 10 CHARACTERS OR LESS

USER: LENTER]

SYSTEM: # OF MARCH UNITS = 3

ENTER # OF MARCH UNITS (MAX 10)

USER: [ENTER]

SYSTEM: IN SERIAL NO. 3 THIS IS MARCH UNIT NO. 1

OF VEHICLES IN MU = 195 ENTER # OF VEHS. IN MU

USER: [ENTER]

SYSTEM: MARCH UNIT NAME = 4-40 FA

ENTER MARCH UNIT NAME, 10 CHARACTERS OR LESS

USER: [ENTER]

SYSTEM: IN SERIAL NO. 3 THIS IS MARCH UNIT NO. 2

OF VEHICLES IN MU = 72 ENTER # OF VEHS. IN MU

USER: [ENTER]

SYSTEM: MARCH UNIT NAME = A/4-441 AD

ENTER MARCH UNIT NAME, 10 CHARACTERS OR LESS

USER: [ENTER]

SYSTEM: IN SERIAL NO. 3 THIS IS MARCH UNIT NO. 3

OF VEHICLES IN MU = 50 ENTER # OF VEHS. IN MU

USER: [ENTER]

SYSTEM: MARCH UNIT NAME = A/55 EN

ENTER MARCH UNIT NAME, 10 CHARACTERS OR LESS

SYSTEM: THIS IS SERIAL NO. 4

SERIAL NAME = 1BDE FSB

ENTER SERIAL NAME, 10 CHARACTERS OR LESS

USER: [ENTER]

SYSTEM: # OF MARCH UNITS = 1

ENTER # OF MARCH UNITS (MAX 10)

USER: [ENTER]

SYSTEM: IN SERIAL NO. 4 THIS IS MARCH UNIT NO. 1

OF VEHICLES IN MU = 156 ENTER # OF VEHS. IN MU

USER: [ENTER]

SYSTEM: MARCH UNIT NAME = 1BDE FSB

ENTER MARCH UNIT NAME, 10 CHARACTERS OR LESS

USER: [ENTER]

SYSTEM: THIS IS SERIAL NO. 5

ENTER SERIAL NAME, 10 CHARACTERS OR LESS

USER: TF4-23

SYSTEM: ENTER # OF MARCH UNITS (MAX 10)

USER: 4

SYSTEM: IN SERIAL NO. 5 THIS IS MARCH UNIT NO. 1

ENTER # OF VEHS. IN MU

USER: 21

SYSTEM: ENTER MARCH UNIT NAME, 10 CHARACTERS OR LESS

USER: B/4-23

SYSTEM: IN SERIAL NO. 5 THIS IS MARCH UNIT NO. 2

ENTER # OF VEHS. IN MU

USER: 36

SYTEM: ENTER MARCH UNIT NAME, 10 CHARACTERS OR LESS

USER: HHC/4-23

SYSTEM: IN SERIAL NO. 5 THIS IS MARCH UNIT NO. 3

ENTER # OF VEHS. IN MU

USER: 27

SYSTEM: ENTER MARCH UNIT NAME, 10 CHARACTERS OR LESS

USER: C/4-23

SYSTEM: IN SERIAL NO. 5 THIS IS MARCH UNIT NO. 4

ENTER # OF VEHS. IN MU

USER: 19

SYSTEM: ENTER MARCH UNIT NAME, 10 CHARACTERS OR LESS

USER: A/4-23

SYSTEM: THIS IS CHECKPOINT !

ENTER HALT TIME IN MINUTES

USER: [ENTER]

SYSTEM: THIS IS CHECKPOINT 2

ENTER HALT TIME IN MINUTES

USER: [ENTER]

SYSTEM: THIS IS CHECKPOINT 3

HALT TIME = 30

ENTER HALT TIME IN MINUTES

USER: 0

CORP. DESCRIPT. CONTRACT APPROPRIATE PROPERTY DESCRIPTION

SYSTEM: THIS IS CHECKPOINT 4

ENTER HALT TIME IN MINUTES

USER: [ENTER]

SYSTEM: THIS IS CHECKPOINT RP

ENTER HALT TIME IN MINUTES

APPENDIX D

SAMPLE OUTPUT

HASTY MOVE WITH STAGGERED STARTS FILE IS 18DE

ROAD MOVEMENT TABLE

MAX PACE(KMPH) = 35
AVG SPEED FOR 1ST UNIT(KMPH) = 32
LENGTH OF COLUMN(KM) = 79.1
AVG VEHICLE LENGTH(METERS) = 8
VEHICLE DENSITY(VPKM) = 8.9

gand betatie assemen kannon bulding propess bessea hospassa kannonka kanzaza semona ee B

VEHICLE INTERVAL(METERS) = 50
MARCH UNIT INTERVAL(KILOMETERS) = 3
SERIAL INTERVAL(KILOMETERS) = 5

		NUMBE								
SERIAL NO	NO NO	OF VEHIC		POINT	DUE IN TIME (HHMM DD)	RELEASE TIME (HHMM DD)	REMARKS		PA((KMPH)	E (MPH)
1	1	28	1 2 3 4 RP	SP 0738- 0826- 0904- 1004- 1121-	+00 +00 +00	0703+00 0741+00 0829+00 0939+00 1009+00 1124+00	TF4-77 A/4-77 30 -MINUTE	REST	35.0 30.0 34.6 20.0 34.1	21.7 18.6 21.4 12.4 21.1
	2	42	SP 1 2 3 4 RP	0710- 0747- 0835- 0914- 1014- 1132-	+00 +00 +00 +00	0714+00 0752+00 0840+00 0951+00 1021+00 1136+00	HHC/4-77 30 -MINUTE	REST	35.0 30.0 34.4 20.0 33.6	21.7 18.6 21.3 12.4 20.9
	3	23	SP 1 2 3 4 RP	0722- 0800- 0848- 0926- 1026- 1143-	+00 +00 +00 +00	0724+00 0803+00 0851+00 1000+00 1030+00 1145+00	8/4-77 30 -MINUTE	REST	35.0 30.0 34.7 20.0 34.3	21.7 18.6 21.5 12.4 21.2
	4	32	SP 1 2 3 4 RP	0731+ 0809+ 0857+ 0935+ 1035+ 1153+	+00 +00 +00 +00	0734+00 0812+00 0900+00 1010+00 1040+00 1156+00	C/4-77 30 -MINUTE	REST	35.0 30.0 34.5 20.0 34.0	21.7 18.6 21.4 12.4 21.1
2	1	21	SP 1 2 3 4 RP	0745+ 0823+ 0911+ 0949+ 1049+ 1206+	-00 -00 -00 -00	0747+00 0825+00 0913+00 1023+00 1053+00 1208+00	TF4-2 B/4-2 30 -MINUTE	REST	35.0 30.0 34.7 20.0 34.3	21.7 18.6 21.5 12.4 21.3

	2	36	SP 1 2 3 4 RP	0745+00 0331+00 0919+00 0958+00 1058+00 1216+00	0757+00 0835+00 0923+00 1034+00 1104+00 1219+00	HHC/4-2 30 -MINUTE REST	35.0 30.0 34.5 20.0 33.8	21.7 18.6 21.4 12.4 21.0
	3	27	SP 1 2 3 4 RP	0805+00 0843+00 0931+00 1009+00 1109+00 1226+00	0803+00 0346+00 0934+00 1043+00 1113+00 1229+00	C/4-2 30 -MINUTE REST	35.0 30.0 34.6 20.0 34.1	21.7 18.6 21.5 12.4 21.2
	4	19	SP 1 2 3 4 RP	0815+00 0353+00 0941+00 1019+00 1119+00 1235+00	0817+00 0855+00 0943+00 1052+00 1122+00 1237+00	A/4-2 30 -MINUTE REST	35.0 30.0 34.7 20.0 34.4	21.7 18.6 21.5 12.4 21.3
3	!	195	SP 1 2 3 4 RP	0826+00 0903+00 0951+00 1032+00 1132+00 1302+00	0845+00 0926+00 1014+00 1135+00 1206+00 1321+00	1BDE CS 4-40 FA 30 -MINUTE REST	35.0 30.0 32.2 20.0 29.4	21.7 18.6 20.0 12.4 18.2
	2	72	SP 1 2 3 4 RP	0907+00 0944+00 1032+00 1111+00 1211+00 1332+00	0914+00 0952+00 1040+00 1154+00 1224+00 1339+00	A/4-441 AD 30 -MINUTE REST	35.0 30.0 33.9 20.0 32.7	21.7 18.6 21.0 12.4 20.3

COCCOCC DESCRIPTION DESCRIPTION CONTROL SERVICE DESCRIPTION

A STATE OF THE STA	(Cara	of the sales	i energia	ale distribution distribution		herenegenerenen beter	atente alente.	(Balkalka)
×								
3								
2555555								
N N								
•								
	•	50	C D	0924+00	0929+00	A/55 EN	35.0	21.7
<u>k</u>	3	50	SP 1	1002+00	1008+00	A/33 EN	30.0	18.6
			2 3	1050+00 1129+00	1056+00 1207+00	30 -MINUTE REST	34.3 20.0	21.2 12.4
			4	1229+00	1237+00		33.4	20.7
			RP	1348+00	1353+00			
4	1	156	SP	0940+00	0955+00	1BDE FSB 1BDE FSB	35.0	21.7
	,	130	1	1017+00	1035+00	.001	30.0 32.8	18.6 20.3
X			2 3	1105+00 1146+00	1123+00 1243+00	30 -MINUTE REST	20.0	12.4
			4 RP	1246+00 1413+00	1313+00 1428+00		30.3	18.8
<u>\$</u>			KP	1413700	1420+00			
4 - A - A - A - A - A - A - A - A - A -								
R								
S.								
8								
<u> </u>								
8								
*					D-3			
20 1000000 3000000 30								
8								
18								
8								
8								
	<u> </u>		3/3/3/3	40000			*	

TIME ANALYSIS -- FULL COLUMN

START TIME = 0700+00 COMPLETION TIME = 1428+00 MARCH TIME (INCLUDING HALTS) = 7:28

SERIAL NO	SERIAL NAME	TIME LEFT SP	TIME CLEARED SP	TIME ARRIVED RP	TIME CLEARED RP	PASSTIME AT RP
1	TF4-77	0700+00	0734+00	1121+00	1156+00	00:35
2	TF4-2	0745+00	0817+00	1206+00	1237+00	00:31
3	1BDE CS	0826+00	0929+00	1302+00	1353+00	00:51
4	1BDE FSB	0940+00	0955+00	1413+00	1428+00	00:15

ROUTE DESCRIPTION

ROUTE IS 310 ROAD SEGMENT	ie DISTAN	ICE	MAX RAT OF TRAV	
303.1	(Ki4)	(MI)	(KMPH)	(MPH)
1	22	14	35	22
2	24	15	30	19
3	22	14	35	22
4	10	6	20	12
5	44	27	35	22

Received account account and account accou

(THIS PAGE INTENTIONALLY LEFT BLANK)

APPENDIX E MOVEPLAN EVALUATION QUESTIONNAIRE (USER FEEDBACK FORM)

- 1. PURPOSE. The purpose of this questionnaire is to obtain feedback from users on the utility of and potential enhancements for MOVEPLAN.
- 2. BACKGROUND. MOVEPLAN was developed by analysts assigned to the Combined Arms Operations Research Activity (CAORA), Fort Leavenworth, Kansas in 1985. MOVEPLAN was developed as a prototype decision aid to assist tactical planners to develop a unit movement plan. MOVEPLAN was designed to be robust and flexible to enable Army-wide use and to support both detailed unit movement planning and to provide logic for analysis of large force movement on multiple independent routes. Current anticipated enhancements to MOVEPLAN include representation of unit movement from assembly areas to start point and from release point to final positions. Other enhancements may be implemented based on user feedback provided by completion of this questionnaire.

The transfer of the control of the c

3. PROCEDURE. MOVEPLAN users should complete the questionnaire and multiple observation sheets and mail completed materials to:

Commander
USACAORA
ATTN: ATOR-CAS-CF
Ft. Leavenworth, KS 66027-5220

MOVEPLAN SURVEY SHEET

STATE TO SERVICE TO SERVICE TO SERVICE SERVICES SERVICES

١.	USER'S NAME AND RANK:			
2.	USER'S UNIT ADDRESS:			
3.	USER'S DUTY POSITION:			
4.	USER'S PHONE NUMBER:			
5.	SRIEFLY DESCRIBE WHY Y	OU USE HOVEPLAN:		
6.	INDICATE FREQUENCY OF	USE (Circle One):		
	a. During Garrison Op	erations.		
	DAILY	WEEKLY	MONTHLY	NEVER
	b. During Field Opera	ations.		
	DAILY	WEEKLY	MONTHLY	NEVER

7.	INDICATE THE	EASE OF USE OF	THE USER'S MANUAL	(Circle One):	
	VERY EASY	FASY	DIFFICULT*	VERY DIFF	ICULT*
on	*If you circle		or very difficult t	hen please make	suggestions
8.	INDICATE THE	EASE OF PROGRA	M OPERATION (Circl	e One):	
	VERY EASY	EASY	DIFFICULT*	VERY DIFF	ICULT*
	*Suggestions	for improvemen	its?		
9.	DOES MOVEPLAN	SUPPORT MOST	OF YOUR MOVEMENT P	LANNING MEEDS?	(Circle One)
		YES	NO*		
	*What needs to	o be added or	changed?		
10.	DOES MOVEPLAN	N OPERATE IN A	A LOGICAL AND TIMEL	Y MANNER FOR YO	UR NEEDS?
	,	YES	ио*		
	*What needs to	o be changed?			

11.	PLEASE	PROVIDE	GENERAL	COMMENTS	BELOW:

STATES OF THE PROPERTY OF THE

proposes accepted accorded processes statement lessage

12. PLEASE COMPLETE AN EVALUATION WORKSHEET FOR EACH SPECIFIC OBSERVATION OR SUGGESTED IMPROVEMENT (PLEASE PROVIDE DETAILS).

MOVEPLAN EVALUATION WORKSHEET

OBSERVATION/PROBLEM:		
DISCUSSION:		

Source recovered recovered responsed responsed repression appropriate recovered recovered recovered responsed

RESOLUTION:

(THIS PAGE INTENTIONALLY LEFT BLANK)

SEEZE INSCREECE CHARACT CHARACTER SERVINGS PROBLEMS

property expressed between

	APPENDIX F	
	DISTRIBUTION	
		No. Copi
•	Defense Technical Information Center ATIN: DTIC-TCA Cameron Station Alexandria, VA 22314	2
	US Army Library Army Study Documentation and Information Retrieval System (ASDIRS) ANRAL-RS, ATTN: ASDIRS Room 1A518 Pentagon Washington, DC 20310	1
	Headquarters, Department of the Army ATTN: SAUS-OR Washington, DC 20310-0102	1
	Headquarters, DA ATTN: DAMO-ZD	1
	Director Concepts Analysis Agency 8120 Woodmont Ave. Bethesda, MD 20814-2797	1
	Commander Army Materiel Systems Analysis Activity ATTM: AMIXSY-CM (CPT Bartley) Aberdeen Proving Ground, MD 21005	1
	Director Office of the Chief of Transportation ATIN: ATSP-OCT Fort Eustis, VA 23604-5000	1
	Director US Army TRADOC Operations Research Activity White Sands Missile Range, NM 88002	1
•	Director US Army TRADOC System Analysis Activity	2
	USATRASANA ATTH: ATOR-TSL (Tech Library)	ì
	F-1	

	No. Copie
Chief US Army TRADOC Research Element P.O. Box 8692	1
Naval Postgraduate School Nonterey, CA 93943	
Dr. Sam Parry Code 55PY Department of Operations Research Haval Postgraduate School	1
Or. Atomael Soveretgn C3I Curriculum Code 74 Naval Postgraduute School	ļ
Debuty Commanuer US Army Combined Arms Combat Developments Activity ATTM: ATZL-CAC-C	1
Fort Elevenworth, KS 66027 Commander US Army Combined Arms Operations Research Activity ATTN: ATOR-CAQ	1
SACAORA AITH: ATOR-CAI-D (Tech Info)	!
Deputy Commandant US Army Command and General Staff College ATTN: ATZL-SWS (C.A.R.L.)	1
USACGSC ATTN: ATZL-SWT	1
JSACG3C ATTN: ATZL-SWB	1
USACG3C ATTH: ATZL-SWV	ļ
Chief, CECOM ATTN: AMSEL-FL-SDSD (C2MUG)	ļ
Conmander US Army Logistics Center Fort Lee, VA 23:01	, i

GOODDING COCCOCCO BOOKS COCCOCCO POSSÓZ

San Sound Control

المرافقة المرافقة المتحديدة المتحديدة المرافقة